

# Nero Burning ROM

Version 5.x /6.x

1. Launch Nero.
2. Choose File, Burn Image and you'll be presented with a dialog box.
3. Click on the Files of type: dropdown box and select All Files (\*.\*)).
4. Select the .ISO file you downloaded then press Open.
5. Next, Nero will show another dialog box of CD burning options. Accept the defaults:
  - Type of Image: Data Mode 1
  - Block size (Bytes): 2048
  - Image header (Bytes): 0
  - Image trailer (Bytes): 0
6. Choose OK.
7. The Write CD dialog box should appear next.
8. Make sure **Write**, **Finalize CD**, and **Disc-At-Once** are checked, then choose Write.

## Tips:

- You must use the "Finalize CD" and "Disc-At-Once" option in Nero, or you will get the error: "FATAL ERROR: Installation of side by side assemblies failed" during setup.
- You must specify \*.\* for the file type to see the .ISO file.

# Padus DiscJuggler

Free Trial at 1x burn speed

<http://www.padus.com/>

1. Open Disc Juggler.
2. Click the New icon, or select File/New from the menu.
3. Select "CD Image to CD Recorder"
4. Under Source, enter the pathname to the .ISO image file, or click the Icon next to the text box to open a Browse dialog.
5. Under Action, select "Write and Verify" from the drop-down list.
6. Under Destination, ensure your CD-R/CD-RW drive is selected.
7. Under Method, Select the desired write speed using the slider.
8. Click the Start button. The burn process will begin.

# WinOnCD

Power Edition Version 3.8

1. Start WinOnCD and choose to create a Track Image.
2. Drag the .ISO file into your Track Image window.
3. Click on disc, to start burning the CD

# NTI CD Maker 2000 Professional

Version 4.2.68

1. After starting program, click on 'Custom CD' icon on the "Welcome to CD Maker!" window.
2. This will open the 'Custom CD' window, which includes a Windows Explorer and a Custom CD Track Layout section.
3. On the left side of the Windows Explorer, navigate to and click on the folder where the downloaded ISO file is located.
4. On the right side of the Windows Explorer window, click and hold on the filename of the downloaded ISO file.
5. Drag the file to the bottom portion of the CD Maker window (the 'Custom CD Track Layout:' section).
6. Insert a blank CD into the CD drive.
7. Click on the 'Step 2' button on the left side of the CD Maker window.
8. The ISO image will now be extracted and written to the CD.
- 9.

# Roxio /Adaptec EZ CD Creator

Version 4.x/5.x/6.x

Method 1:

1. Launch Easy CD Creator
2. Choose File, Create CD from CD Image... and you'll be presented with a dialog box.
3. Click on the "Files of type:" dropdown box and select "ISO Image Files (\*.ISO)"
4. Select the .ISO file you downloaded then press Open.
5. At the CD Creation Setup dialog box, make sure the Write Method is set to **Disc-At-Once** and **Close CD**.
6. Select the desired write speed and create options, if necessary, then press OK to begin recording.

**Note:** In EZCD Creator you **must** change the drop down to reflect \*.ISO rather than the default to see the file.

Method 2:

1. Navigate in Explorer to the .ISO file you have downloaded, and double click on it.
2. Choose the write speed you want to use.
3. You will have three Create options:
  - Test
  - Test & Create CD
  - Create CDYou can use Create CD or Test and Create CD
4. At the CD Creation Setup dialog box, make sure the Write Method is set to **Disc-At-Once** and **Close CD**
5. Select the desired write speed and create options, if necessary, then press OK to begin recording.